

## Windows 10 Enable microphone and camera

03.07.2024 11:30:24

FAQ-A	rtikel-	Ausd	ruck
-------	---------	------	------

				FAQ-Artikel-Ausdruck
Kategorie:	Weitere Dienste::PC-Services	Bewertungen:	5	
Status:	öffentlich (Alle)	Ergebnis:	90.00 %	
Sprache:	en	Letzte Aktualisierung:	10:54:11 - 09.09.20	22
Schlüsselwörter				
CampusSachsen Kamera N	Aikrofon Windows10			
Lösung (öffentlich)				
In coordination with the Ur following security settings Downloads Portal have be	nit 3.5 Information Security of the TU Dresden, the for the Windows 10 distribution from the MS en incorporated:			
<ul> <li>No transmission of Windo</li> <li>Disable access to microp (This prevents accidental of that they cannot be seen of</li> </ul>	ows usage data to Microsoft hone and camera for all applications or third-party activation of these components, so or heard in your room via the computer).			
Note: Similar settings may installation by your local I	have been made for other versions of Windows during administration.			
Concerned Windows versio - Windows 10 LTSC - Windows 10 Education 19	ons 909 or older			
Prerequisite - You need administrative	access to your computer.			
Otherwise, please contact the necessary steps via re offers [1]ISL Light, which r contact person in the proc	your local IT administration, which can also perform mote access to your computer. For this purpose, ZIH nust be used in [2]administrative mode by your ess.			
Activating microphone and	camera Script for enabling			
In the attachment of the a "enable_devices.cmd". Exe and camera are now ready	rticle you will find the script ecute this by double-clicking on it. The microphone / for use. It is not necessary to restart the computer.			
Manual instruction				
The activation is done by a It is important to distinguis button. The required key is [L] and [R].	a change in the Windows registry (registry entries). sh whether you work with the left or right mouse s indicated in square brackets with capital letters			
<ul> <li>Click on Windows icon (S → More [L] →Run as admin - Usually the administrator your account already has I with "YES".</li> <li>A black window appears:</li> </ul>	tart) [L] $\rightarrow$ Windows System [L] $\rightarrow$ Command prompt [R] istrator [L] password is now requested. Enter the password. If the necessary rights, confirm the appearing query			
- Enter here the command purpose - select the text after a da - copyx it to the Windows « - switch to command prom - paste the content from th - compare text line (search - confirm input (press Enter	lines from the box below (5) one by one. For this sh completely Clipboard (CTRL+C) opt (the black window is active) ne Windows clipboard (CTRL+V) n for Microphone, Camera or Apps) er or Return)			
<ul> <li>If the desired text is not i and try again with the des</li> <li>reg add HKLM\SOFTWARI</li> <li>LetAppsAccessMicrophone</li> <li>reg add HKLM\SOFTWARI</li> <li>LetAppsAccessCamera /t F</li> <li>reg add HKLM\SOFTWARI</li> <li>/t REG_DWORD /d 0x0 /f</li> </ul>	n the windows, delete the line (backspace key) ired line. E\Policies/Microsoft\Windows\AppPrivacy /v ;/t REG_DWORD /d 0x1 /f E\Policies\Microsoft\Windows\AppPrivacy /v REG_DWORD /d 0x1 /f E\Policies\Microsoft\WindowsStore /v DisableStoreApps			
-				
Now close the command p	rompt.			
<ul> <li>Microphone and camera not necessary.</li> </ul>	are now ready for use. A restart of the computer is			
[1] https://rsupport.zih.tu- [2] https://help.islonline.co	dresden.de/ om/41054/283986			